


HOW TO ADMINISTER ubroseal CORRECTLY



1 Ensure animals are appropriately restrained in a clean environment



2 Keep syringes clean and DO NOT immerse in water



3 Clean disposable gloves should be worn and washed and disinfected (or changed) between cows



4 If teats are obviously dirty then clean off dirt with moistened towels and dry thoroughly



5 Dip teats in a rapid acting pre-dip, leave for 30 seconds, then wipe each teat completely dry with separate disposable paper towels



6 Strip fore milk into a strip cup and discard



7 Thoroughly disinfect the whole surface of the teat with a disposable swab soaked in surgical spirit. Clean the teats furthest away from you first




8 Gently scrub each teat end with new individual, disposable, surgical spirit swabs or teat wipes provided, until both teat end and swab/wipe are visibly clean



9 Remove the cap from the teat sealant intramammary tube, being careful not to touch the nozzle



10 Pinch the base of the teat where it joins the udder



11 Infuse the contents of the syringe into the teat avoiding contaminating the teat end



12 Infuse teats in the opposite order to cleaning, i.e. treat the quarters closest to you first



13 Deposit a small quantity of sealant in the teat canal as you remove the syringe



14 DO NOT massage the product into the udder



15 Apply a post-milking teat disinfectant and confine the treated cows to a yard where they should stand for at least 30 minutes to allow the teat canal to close